



Elma Schmidbauer GmbH · Postfach 280 · D-78202 Singen

Release Notes – Elmasolvex VA R014

Changes to the Elmasolvex VA software from version R013 to R014


New:

N1


The software now supports an alternative controller for the multi-way valve drive.

N2

Displaying and resetting the media exchange reminders have been modified. When a counter reaches the set threshold after finishing a cleaning program, this is indicated on the display. Before, this display allowed the user to select whether they want to be reminded again, or whether they want to reset the counters (after query). These options are no longer available in the present display, only the current counter score is shown. Now, in the program selection screen a new icon is shown on the left side which can be used to quickly call up the current counter scores.



If a counter has gone beyond the threshold, the icon shows an additional yellow exclamation mark.



This screen now shows a new icon in the left bottom: the user can use it to call up the settings for the media exchange reminders which allows them to reset the counter quickly, if required.



Elma Schmidbauer GmbH · Postfach 280 · D-78202 Singen

Bug fixes:

F1

A bug was fixed which had led to the counter score display in the menu „media exchange reminders“ not being updated.